

FabMo1.6.0 Offline (AP Mode) Update Instructions For Handibots

These instructions provide a method to update Handibot (FabMo) software using the local AP connection mode. This allows you do the major 1.6.0 update, even if you do not have an internet connection to your tool, or if your are experiencing a poor internet connection to it.







First, download the consolidated update package (.fmp) from the link below using a computer or device that with an internet connection:

https://github.com/FabMo/FabMo-Engine/releases/download/v1.6.0/fabmoconsolidated-engine-1.6.0-updater-2.3.1.fmp

This is an 84MB file, and may take some time to download on a slow connection. It also may provoke a warning from some virus checkers. Such warnings can be ignored.


Once you have downloaded the file to your computer, you no longer need the internet connection.



Turn on your Handibot and connect to it in AP mode from your PC or device.

(Instructions for using different connection modes can be found on the Handibot website or at: docs.handibot.com.)

Go to the Updater window by opening the Configuration manager and *clicking on the version number* in the upper right corner of the menu (or at the bottom of a drop-down menu)




The Updater window provides full management of updates (after 1.6.0, the update process will be simplified and done from the main menu.)


click Software Updates → then Update With File...



6 Browse and select the file you downloaded in Step 2 ...




The update takes about 10 minutes to complete. During the course of the update, you will see messages like those below. They are **normal and expected.** Your computer will disconnect from the Handibot several times and may not reconnect.



- a. 10 minutes after the start of the update, turn your Handibot off then back on again.
- b. Reconnect from your computer to your Handibot in AP mode. You may need to refresh the screen a few times.

Your can return to the Updater window to make sure the new software installed correctly.





Click "Goto Dashboard" to return to the FabMo home screen ... (almost done)






You'll be returned to the FabMo home page.


Now, just a couple more details:

- · Go to the Configuration manager
- Make sure your tool profile is "Handibot 2" (use "Handibot 1" for a Developer Edition tool that has been updated to FabMo)



12

Finally, you may discover icons for more than one copy of an app on your home page. The first copy can be deleted by click and holding the icon until an "x" is visible, then clicking on the "x" to delete the copy.



Congratulations! The update is complete.